OUTDOOR SETUP: STANDARD

THIS SETUP WILL WORK FOR BOTH INDIVIDUALS AND/OR FOR GROUPS





Shutter Speed Reference Chart

(Lighting Condition Prior to Taking Picture of Subject)

1/250th - If Subject Shadow CAN be Seen

1/125th - If Subject Shadow can NOT be Seen

1/60th - Low Light

1/30th - Very Low Light (tripod recommended)


SUBJECT

- **Subject is Positioned 12ft from** Light/Flash
- **Subject Should be Angled Slightly Away from Camera and AWAY** from the Sun
- 12ft Mark is Where the Individual **Subject is Positioned AND Where** the Front Row of the Group is **Positioned**

MAIN LIGHT

- 18" Silver Reflector Without **Diffusion Sock**
- **Bottom of Reflector Should be 5ft** from Ground
- **Light is Positioned 12ft from Subject Position**
- **Light Should be Placed on Opposite Side of Where Sun is Striking Subject**
- Light Metered at: F/11

12ft



LIGHT METER


- Mode: Flash
- ISO: 100
- **Shutter Speed: 125**
- F/Stop: F/11
- **Take Meter Reading from Subject Chin Position**
- **Point Light Meter Towards Camera Position**
- Make Sure no Direct Sunlight is **Hitting White Dome**
- Make Sure White Dome is Not Covered

SETUP

STEP ONE: Mark Subject Position STEP TWO: Mark Light/Flash Position STEP THREE: Set Up Light/Flash **STEP FOUR:** Meter Light/Flash STEP FIVE: Set Up Tripod and Camera **STEP SIX**: Take Test Shot

CAMERA SETTINGS

- ISO: 100
- F/Stop: F/11
- Shutter Speed: 1/30 to 1/250 (See Shutter Speed Reference Chart)
- White Balance: Flash
- Camera/Photographer is **Positioned Directly Beside Light**



Outdoor Sports - Individuals & Little League Groups - 2017L

Case Inventory

☐ D7200 Camera Body ☐ 18-105mm Lens ☐ Lens Hood ☐ 3 Genuine Nikon Camera Batteries - Charged ☐ Camera Battery Charger ☐ Heavy Duty Light Stand Lighting ☐ 2 Alien Bee B800's ☐ 2 Power Cords - Short ☐ Studio Lights Tested ☐ 2 1/4" Stereo Sync Cords ☐ 2 Hot Shoe Adapters ☐ 2 CyberSync Transmitters ☐ 2 CyberSync Receivers \Box 2 CyberSync Sync Cords – Miniature to $1\!\!/\!_{\!4}^{\!\!\!4}$ ☐ 18" Silver Reflector (Spill Kill) ☐ Vagabond Power Pack – Charged ☐ Extra Vagabond Battery - Charged ☐ Light Meter – Battery Checked ☐ PhotoMatch Tablet - Charged ☐ Keyboard ☐ Power Cord ☐ Tablet Bracket to Mount on Stand ☐ Tablet Hood □ 2 D7100/7200 Camera USB Cables ☐ Double USB Adapter □ 2 Scanners ☐ Hot Spot Router ☐ Sales Table Tablets - Charged □ 4 Memory Cards ☐ Memory Card Envelopes ☐ Zippered Card Pouch ☐ Tape Measure ☐ Gaffer Tape ☐ Hoodman Viewer ☐ Sun Umbrella Kit ☐ Stool ☐ Sample Display ☐ Registration Tablets - Charged ☐ Photo Props ☐ BU Sequence Cards, Stringer, Pens ☐ Boundary Stakes ☐ Boundary Ribbon

Setup & Settings

0	etup & Settings
S	☐ Setup with Sun Over Subject's Shoulder
<u>o</u>	☐ Mark spot for Studio Light
	☐ Mark the spot for the subject and group at 12ft
0	☐ Feet marks should be spread apart
ζο	☐ Set marks at angle so subject faces away from sun
S	☐ Setup studio light w/ reflector bottom 5ft off ground
e E	☐ Point reflector towards subject position
Setup & Settings	□ Power up Studio Light plugged into Vagabond
<u> </u>	☐ Modeling light/bulb is OFF (or removed)
S	☐ Modeling bulb has been removed
	☐ Set top power slider to ½ Power
	☐ Set Light Meter to "Flash", ISO100, 1/125 Shutter
	□ Verify no direct sunlight is hitting meter dome
	☐ Verify hand is not blocking meter dome from strobe
	☐ Meter Studio Light to F/11 (12ft from subject mark)
	☐ Setup Tripod with Camera
	☐ Verify Camera Settings
	☐ Camera - Shooting Mode = M (Manual)
	☐ Camera - Quality = S Basic (6MP on D7100)
	☐ Camera - WB (White Balance) = K (Kelvin) 5560°
	☐ Camera - ISO = 100
	☐ Camera - Shutter Release Mode = S (Single)
	☐ Camera - Auto Focus switch on body to AF
	☐ Camera - Lens Auto Focus Switch = A or MA (NOT M)
	☐ Camera - Focus Mode = AF-S (Single)
	☐ Camera - Auto Focus Points Area Mode = Auto
	☐ Front of Lens Clean & Lens Hood Properly Seated
	☐ Camera - Image Review Settings –Focus Points On
	☐ Camera – Review Mode – Focus Points Screen
	☐ Camera - Aperture (f/stop) f/11
	☐ Camera - Shutter Speed – 1/30 to 1/250 See Chart Below
	Shutter Speed Reference Chart
	(Lighting Condition Prior to Taking Picture of Subject)
	1/250 th - If Subject Shadow <u>CAN</u> be Seen
	1/125 th - If Subject Shadow can <u>NOT</u> be Seen
	1/60 th - Low Light
	1/30 th - Very Low Light (tripod recommended)
	-IMPORTANT-
	If using a Non-Nikon Camera, check owner's
	manual for maximum flash sync speed. Some
	camera makes/models have a slower sync speed than 1/250 th
	☐ Mount CyberSync Transmitter on camera
	☐ Setup Hot Spot
	□ Setup Tablet

☐ Verify Tablet, SNAP, PhotoMatch, DigiCam Settings